


Table of Contents

Chapter 1 BAL plugin installation in WINDOWS 2

 1.1 Prerequisites 2

 1.2 Download BAL PLUGIN..... 2

 1.3 Installation procedure BAL PLUGIN 4



Chapter 1 BAL plugin installation in WINDOWS

1.1 Prerequisites

The BAL’s installation requires as a prerequisite that you have already installed ELECTRUM and have created a wallet. If you are not in this situation, go to the electrum website, to the DOWNLOAD section and install the WINDOWS INSTALLER version following the instructions

Electrum web site - Download section

1.2 Download BAL PLUGIN

Go to [HTTPS://BITCOIN-AFTER.LIFE](https://bitcoin-after.life)

BAL plugin installation in WINDOWS



Scroll down the page to the ‘Plugin Operations’ section

Plugin Operations

The plugin generates a transaction with Locktime set to a future date; the transaction is signed and sent to one or several Will-Executors, who will take care in retaining the transaction and send it at the expiry date.


In order to provide economic incentives for the Will-Executor to keep and broadcast the transaction, an output will contain a fee payment, which will be received only when the heredity transaction is confirmed in the block chain.

[Bitcoin After Life Electrum Plugin](#)

Click on “Bitcoin After Life Electrum Plugin “ or this link Bal Plugin and Download the plugin




Check that you have installed ELECTRUM in the following folder **C:\Program Files (x86)\Electrum\electrum**



We need this during installation of the plugin if we have changed the standard folder. The standard folder is **C:\Program Files (x86)\Electrum\electrum\plugins**

BAL plugin installation in WINDOWS




Install the plug-in following the on-screen instructions, making sure that the destination folder is the electrum plug-in folder, chosen when installing **ELECTRUM**

1.3 Installation procedure BAL PLUGIN


1) Close ELECTRUM, if it is open

2) Find
bal-




the file

electrum-plugin.tar.bz2, normally found in the **DOWNLOAD** folder



3) Use a program like 7-zip, WinRAR, or WinZip to open the file.


BAL plugin installation in WINDOWS




I used 7-zip.

BAL plugin installation in WINDOWS

4) Snap the two windows




5) Drag or extract the contents of the compressed file into the **Electrum plugin folder**.



Should Windows ask you to grant permissions to access and copy the files to the target directory, click the 'CONTINUE' button.


6) The “**BalElectrumPlugin**” folder should now be in the *Electrum Plugins* folder.




Close any open windows and proceed with the steps.

6) Open Electrum

BAL plugin installation in WINDOWS




7) Click on Tools → Plugin




8) See activatable or active pluginsPlugin

BAL plugin installation in WINDOWS




9) Click on the check box to the left of B.A.L. to activate it and click on **CLOSE**




Press the 'OK' button and after the 'CLOSE' button

10) Once back at the main window **CLOSE ELECTRUM**

BAL plugin installation in WINDOWS




11) Reopen Electrum and appear in the programme **HEIRS** e **WILL**




Heirs page

BAL plugin installation in WINDOWS





Will page



and in TOOLS → **WILL EXECUTORS**

BAL plugin installation in WINDOWS



Refer to the manual for a detailed explanation of how the Plugin works.